How to prepare your soil:

Use a bio **Lightmix** substrate, or a **slightly fertilized** organic potting soil (no Allmix!)



(optional)

PREGROW POT

1) Mix **5g** of **STARTREX** per 1L of potting soil. Mix well. Fill your pots with this mixture and make a planting hole.
2) Sprinkle **1g** of **MYCOTREX** into the planting hole.
3) Plant your cutting or seedling.
4) Water your plants with plain water when needed.

FINAL POT

1) Mix **50g** of **STARTREX** per 10L of potting soil. Mix well. Fill your pots with this mixture and make a planting hole.
2) Sprinkle **5g** of **MYCOTREX** into the planting hole.
3) Plant your cutting or seedling.
4) Press the BioTabs 10cm deep into the potting soil.
5) Dissolve 1g BACTREX and 10ml ORGATREX in 1L of water. Water the first time only with 1L of this solution.[2]



When using Autopot, you need to put the BioTabs 10cm from the bottom of the pot, then fill up the pot from the top with substrate and make a planting hole.

Tablespoon	x4	50g
Teaspoon	x1	5g

BioTabs' dosage:



- 1 tab/5L pot
- 2 tabs/10-15L pot
- 3 tabs/20-25L pot
- 4 tabs/30-35L pot
- 5 tabs/50L pot

See other side on how to prepare your soil.

ORGANIC GROW GUIDE

(Dechlorinated) Plain water only

			VEGETATIVE		FLOWERING								
PRODUCTS	(optional) ❶ PREGROW POT WATERING	❷ FINAL POT WATERING	WEEK 1	WEEK 2 ❻	WEEK 1	WEEK 2	WEEK 3 ❸	WEEK 4	WEEK 5	WEEK 6	WEEK 7	WEEK 8	WEEK 9
BACTREX	0,5g/L	1g/L					1g/L						
ORGATREX	5ml/L	10ml/L					20ml/L						
❹ BIO PK 5-8						10ml/L		10ml/L		10ml/L			
❺ BOOMBOOM SPRAY	5ml/L	5ml/L	5ml/L										

❶ **Pregrow pot** (optional)**:** Dissolve 0,5g BACTREX and 5ml ORGATREX in 1L of water. Water the first time only each plant with this solution. All other days use plain water when needed.

❷ **Final pot:** Dissolve 1g BACTREX and 10ml ORGATREX in 1L of water. Water the first time only each plant with 1L of this solution.

❸ **Week 3** of **flowering:** Dissolve 1g BACTREX and 20ml ORGATREX in 1L of water. Water each plant with 1L of this solution once in week 3. All other days use plain water when needed.

❹ **Bio PK 5-8 flowering booster:** Dissolve 10ml of Bio PK in 1L of water. Water each plant with 1L of this solution ONCE in week 2, 4 and 6 of flowering. All other days use plain water when needed.

❺ **Boom Boom Spray:** Dissolve 5ml in 1L of water. Spray your plants' leaves until dripping wet. Use within 6h.

❻ **Long veg:** If your vegetative stage lasts longer than 2 weeks, in week 3 of the vegetative stage press an extra tab 10cm deep into the potting soil.

BIO TABS.NL ORGANIC GROWING

V.2026.01